

5091

LASER[®]

OBDII/EOBD Code Reader & Reset Tool

Change Language Instructions



www.lasertools.co.uk

Instructions

The 5091 code reader can be programmed with two different language sets. From the factory, the 5091 is programmed with the following 5-language set: English, Spanish, French, Portuguese and Swedish.

If required, the 5091 can easily be programmed with an alternative 5-language set that includes: German, Italian, Dutch, Polish and Hungarian.

To change language sets:

Visit: <https://www.lasertools.co.uk/product/5091>

In the **Useful Downloads** section, download the file:


5091_V2_Software.zip

Unzip and then install the 5091 software (NT Wonder) onto your PC or laptop. You will find the NT Wonder icon on your desktop:




Start the software by double-clicking on the icon.

Then connect the 5091 to the computer; the 5091 will power up and it will be recognised as “Device connected” on the NT Wonder window:




On the 5091 code reader, navigate to:
Setup> Language>



The standard 5-language set is displayed:

Language		1/5
✓	English	
	Español	
	Français	
	Portugal	
	Svenska	

On the NT Wonder window, left-click the **Settings** icon.
In the language pane, select Deutsch, then left-click **Apply**:




After a few seconds the NT Wonder software will restart automatically with the language changed to Deutsch:



On the 5091 code reader press and hold the **HELP** button until the **Offline aktualisieren** button is clickable. Now left-click it:



One update file will be visible on-screen. Select this file (click the box), the click on the **YES** button.



The software update to the 5091 will begin. **Do not disconnect** the 5091 from the computer until the process is complete! On the 5091 the screen will go **GREEN** as the first section completes. **Wait** until the screen goes **BLUE** before restarting the 5091 (**RED** button).



After the 5091 code reader restarts you will see that the 5091 language as changed to **Deutsch** and that the new 5-language set has been installed. Use the **down arrow** then press **ENTER** to select another language.



Sprache		1/5
✓	Deutsch	
	Italiano	
	Nederlands	
	Polski	
	Magyar nyelv	

